

---

Subject: Vetusware.com updates: 2020-12-13

Posted by [vetus@vetusware.com](mailto:vetus@vetusware.com) on Sun, 13 Dec 2020 00:00:00 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Microsoft MS-DOS 2.11 [Visual Commuter OEM r1.9]

<https://vetusware.com/download/Microsoft%20MS-DOS%202.11%20%5BVisual%20Commuter%20OEM%20r1.9%5D/?id=16699>

This is the release of MS-DOS provided with Visual Commuter portable computers. Archive also includes the Commuter Operators Guide, MS-DOS manual, Basic Manual, Maintenance Manual with schematics, and SMT No-Slot clock drivers.

MS-DOS 5.0 Spanish 5.0ms (ES)

<https://vetusware.com/download/MS-DOS%205.0%20Spanish%205.0ms%20ES/?id=16700>

Son las 3 imagenes de diskettes (720kb) originales y booteables listas para poder instalar

Tandon AT/SCSI DataPacII / AdPac / Personal DataPac Drivers & Ut 3.0 (NL)

[https://vetusware.com/download/Tandon%20ATSCSI%20DataPacII%20%20AdPac%20%20Personal%20DataPac%20Drivers%20\\_%20Ut%203.0%20NL/?id=16698](https://vetusware.com/download/Tandon%20ATSCSI%20DataPacII%20%20AdPac%20%20Personal%20DataPac%20Drivers%20_%20Ut%203.0%20NL/?id=16698)

Product=Tandon AT/SCSI DataPacII Drivers & Utilities Description=Support for DOS, OS/2, Novell 286 & 386 Release=3.0 Disknum=1 Language=DUTCH Volume=DPUII-30DUT Label=Tandon SCSI Data Pac Drivers DOS, OS/2, Novell 286 & 386 Utility Diskette Rel. 3.0 Dpprep.exe = Menu Driven Format / partition utility for Personal Data Pac Dpcopy.exe = This utility will make image backups of one Data Pac to another. Dppark.exe = locks read/write heads inside data pac for transport Dpeject.exe = Eject Data pack from drive bay DPdiags.exe = Diagnose Datapac Hlprep.exe = High level preperation utility for pac drives (partition, format) Llprep.exe = Low level preperation utility for pac drives (Low Level format) rllsetup.exe = Setup of Tandon RLL controller card for External AD-Pac dpkey.com = Change ejection key assignment lockdp.com = Lock datapac from ejection copydp.com = copy datapac to other pac drive compdp.com = compare datapac with other pac drive revise.com = unknown? ejectdp.com = eject(s) datapac(s) from drive bays unlockdp.com = unlock datapack for ejection dospac.sys = Tandon Dospac installable device driver dpaccess.sys = Tells dos 3.3 that installed ad-pac is partitioned into 40 megabytes and not restricted to 32 mb dos limit. Add the following line to config.sys: device = dpaccess.sys /s64

---